G Render

How to Turn Off the Volume Adjustment for Headset Mics

1. Plug in your headset mic.

2. From the desktop, swipe your finger from the right edge of the screen toward the middle. This will bring up the "Charms" bar. If you are using a desktop, take your mouse to the upper right corner of the screen and drag straight down.

3. Next, click the "Settings" button on the bottom of the list.



4. On the Settings list, press the "Control Panel" option near the top.



5. Depending on your view settings, you will come to one of the following two screens.



or

📲 🥞 👳 🛐

6. If you find yourself on the first screen, simply press "Sound" and proceed to Step

E) (-) x 1 (III) Control Panel & All (Control Panel Items	All Control Panel Items		C
Adjust your computer's settings				View by: Large icons *
Y Action Center	Add features to Window: 8.1	Administrative Tools	AutoPlay	🛐 Color Management
🕖 Credential Manager	Pate and Time	📕 Default Programs	Device Encryption	실 Device Manager
Devices and Printers	Display	🚱 Ease of Access Center 🛛 👌	Family Safety	File History
🗲 Flash Player	Folder Options	🗼 Fonts 📢	HomeGroup	Indexing Options
Intel(R) HD Graphics	Internet Options	🥯 Keyboard	Language	Location Settings
Mouse	Network and Sharing Center	Notification Area Icons	Pen and Touch	Yersonalization
Phone and Modem	Power Options	阈 Programs and Features 🚽	Recovery	👧 Region
RemoteApp and Desktop Connections	Sound	:h Recognition	Storage Spaces	Sync Center
💐 System	Tablet PC Settings	Taskbar and Navigation	Troubleshooting	🍇 User Accounts
Windows Defender	Windows Firewall	iii Windows Mobility Center 🛛	Windows Update) Work Folders
- 🗎 🔮 📴				📖 🔺 🧶 🏲 🕯 л 0

7. If you find yourself on the second screen, first press "Hardware and Sound".



8. Next, press "Manage Audio Devices".

	Hardware and Sound		-	•
→ ↑ ★ → Control Pan	el + Hardware and Sound +	~ C	Search Control Panel	S
Control Panel Home System and Security	Devices and Printers Add a device Advanced printer setup Mouse Windows To Go startup options Change Windows To Go startup options			
lardware and Sound	AutoPlay Change default settings for media or devices Play CDs or other media automatically			
Iser Accounts and Family afety	Sound Adjust system volume Change system sounds Manage audio devices			
ppearance and lersonalization Jock, Language, and Region ase of Access	Power Options Change battery settings Change what the power bottons do Require a password when the computer wakes Change when the computer sleeps Adjust come highltness			
	Display Make text and other items larger or smaller How to correct monitor flicke (defiesh rate)			
	Windows Mobility Center Adjust commonly used mobility settings			
	Pen and Touch Orange tablet pen statistics Turn flicks on and off Set flicks to perform certain tasks Orange touch input settings			
	Tablet PC Settings Calibrate the screen for pen or touch input. Set tablet buttons to perform certain tasks Choose the order of how your screen rotates Specify which hard you write with			
	Cocation Settings Change location settings			
			_	2.08
- 🐸 🔛			8 · P 8 4 4	5/8/29

9. Select "Recording" from the tabs on top.

Panel Hardware and Sound		~ C	Search Control Par	sel
Sound	×			
ds Communications	r setup 🔰 Mouse 🛛 😵 Device Manager			
low to modify its settings:	options			
×	or devices Play CDs or other media automatically			
>	• system sounds Manage audio devices			
adset H540	te what the power buttons do nputer wakes Change when the computer sleeps			
inition Audio	or analler – Adjust screen resolution – Treforate)			
	ettings Adjust settings before giving a presentation			
Set Default 💌 Properties	In flicks on and off Set flicks to perform certain tasks			
OK Cancel Apply				
Calibrate the screen for pe Choose the order of how Location Settings Change location settings	n of this du higher 1. Set tablet buttons to perform certain table 1 your screen rotates 1. Specify which hand you write with			
	la Communications leve to modely its settings: atters 15:45 etition Audio Set Default (* Properties Concest the other of how Choose the other of how Choose the other of how Choose the other of how Choose the other of how	a Communications in the setting: and in the setting: b concomer setting: b concomer settin	in communications: extra condity its setting: extra condition: <	Concentration Settings Choine Setting Choine Seting Choine Setting Choine Setti

10. Select "Microphone Logitech USB Headset H540" and tap "Properties".



11.Select "Custom" from the new set of tabs.

শ্ব	Hardware and Sound			X X
(→ ↑ · A → Control Panel → Hardware and Sound		~ C	Search Control Pan	el P
Sound Sound Playback Recording Sounds Communications r see	tup Mouse 😵 Device Manager			
S Microphone Properties	ans -			
General Listen Custom Levels Advanced	vices Play CDs or other media automatically m sounds Manage audio devices			
Controller Information	it the power buttons do wakes Change when the computer sleeps			
(Generic USB Audio)				
Jack Information No Jack Information Available	ate)			
	s Adjust settings before giving a presentation			
	is on and off Set flicks to perform certain tasks			
Device usage: Use this device (enable) v	but Set tablet buttons to perform certain tasks states Specify which hand you write with			
OK Cancel Apply				
			2	-26 PM
		······································	* 9 4 () _{5/}	15/2014

12. Uncheck "AGC"



13. Press "OK" when you are done.